

XtConvert, XtDirectConvert – invoke resource converters

void XtConvert(*w, from_type, from, to_type, to_return*)

Widget *w*;
String *from_type*;
XrmValuePtr *from*;
String *to_type*;
XrmValuePtr *to_return*;

void XtDirectConvert(*converter, args, num_args, from, to_return*)

XtConverter *converter*;
XrmValuePtr *args*;
Cardinal *num_args*;
XrmValuePtr *from*;
XrmValuePtr *to_return*;

| | |
|------------------|---|
| <i>args</i> | Specifies the argument list that contains the additional arguments needed to perform the conversion (often NULL). |
| <i>converter</i> | Specifies the conversion procedure that is to be called. |
| <i>from</i> | Specifies the value to be converted. |
| <i>from_type</i> | Specifies the source type. |
| <i>num_args</i> | Specifies the number of additional arguments (often zero). |
| <i>to_type</i> | Specifies the destination type. |
| <i>to_return</i> | Returns the converted value. |
| <i>w</i> | Specifies the widget to use for additional arguments (if any are needed). |

The **XtConvert** function looks up the type converter registered to convert *from_type* to *to_type*, computes any additional arguments needed, and then calls **XtDirectConvert**. **XtConvert** has been replaced by **XtConvertAndStore**.

The **XtDirectConvert** function looks in the converter cache to see if this conversion procedure has been called with the specified arguments. If so, it returns a descriptor for information stored in the cache; otherwise, it calls the converter and enters the result in the cache.

Before calling the specified converter, **XtDirectConvert** sets the return value size to zero and the return value address to NULL. To determine if the conversion was successful, the client should check *to_return.address* for non-NULL. **XtDirectConvert** has been replaced by **XtCallConverter**.

XtAppAddConverter(3Xt), XtStringConversionWarning(3Xt), XtConvertAndStore(3Xt), XtCallConverter(3Xt)

X Toolkit Intrinsics – C Language Interface

Xlib – C Language X Interface