## XSetWMName, XGetWMName, XStoreName, XFetchName – set or read a window's WM\_NAME property

```
void XSetWMName(display, w, text prop)
   Display *display;
   Window w:
   XTextProperty *text prop;
Status XGetWMName(display, w, text_prop_return)
   Display *display;
   Window w;
   XTextProperty *text_prop_return;
XStoreName(display, w, window_name)
   Display *display;
   Window w;
   char *window name;
Status XFetchName(display, w, window name return)
   Display *display;
   Window w;
   char **window_name_return;
                Specifies the connection to the X server.
display
text_prop
                Specifies the XTextProperty structure to be used.
text prop return Returns the XTextProperty structure.
                Specifies the window.
w
window_name
                Specifies the window name, which should be a null-terminated string.
window name return
                Returns the window name, which is a null-terminated string.
```

The XSetWMName convenience function calls XSetTextProperty to set the WM\_NAME property.

The **XGetWMName** convenience function calls **XGetTextProperty** to obtain the WM\_NAME property. It returns a nonzero status on success; otherwise, it returns a zero status.

The **XStoreName** function assigns the name passed to window\_name to the specified window. A window manager can display the window name in some prominent place, such as the title bar, to allow users to identify windows easily. Some window managers may display a window's name in the window's icon, although they are encouraged to use the window's icon name if one is provided by the application. If the string is not in the Host Portable Character Encoding, the result is implementation-dependent.

XStoreName can generate BadAlloc and BadWindow errors.

The **XFetchName** function returns the name of the specified window. If it succeeds, it returns a nonzero status; otherwise, no name has been set for the window, and it returns zero. If the WM\_NAME property has not been set for this window, **XFetchName** sets window\_name\_return to NULL. If the data returned by the server is in the Latin Portable Character Encoding, then the returned string is in the Host Portable Character Encoding. Otherwise, the result is implementation-dependent. When finished with it, a client must free the window name string using **XFree**.

XFetchName can generate a BadWindow error.

WM\_NAME The name of the application.

**BadAlloc** The server failed to allocate the requested resource or server memory. **BadWindow** A value for a Window argument does not name a defined Window.

 $XAlloc Class Hint (3X11), XAlloc Icon Size (3X11), XAlloc Size Hints (3X11), XAlloc WMH ints (3X11), XFree (3X11), XSet Command (3X11), XSet Transient For Hint (3X11), XSet Text Property (3X11), XSet WMC Client Machine (3X11), XSet WMC Color map Windows (3X11), XSet WMI con Name (3X11), XSet WMP roperties (3X11), XSet WMP rotocols (3X11), XString List To Text Property (3X11) <math display="block">Xlib-C\ Language\ X\ Interface$