

AIX 5L Version 5.3



AIX Network Data Administration Facility

AIX 5L Version 5.3



AIX Network Data Administration Facility

Note

Before using this information and the product it supports, read the information in "Notices," on page 45.

First Edition (July 2006)

This edition applies to AIX 5L Version 5.3 and to all subsequent releases of this product until otherwise indicated in new editions.

A reader's comment form is provided at the back of this publication. If the form has been removed, address comments to Information Development, Department 04XA-905-6C006, 11501 Burnet Road, Austin, Texas 78758-3493. To send comments electronically, use this commercial Internet address: aix6kpub@austin.ibm.com. Any information that you supply may be used without incurring any obligation to you.

© **Copyright International Business Machines Corporation 2006. All rights reserved.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

About this document	v
How to use this document	v
ISO 9000	v
The AIX Network Data Administration Facility	1
NDAF concepts	1
NDAF commands	5
NDAF deployment models.	6
NDAF security	7
NDAF installation and configuration	9
Managing NDAF	12
Troubleshooting NDAF	37
Additional NDAF command processes	41
NDAF SMIT fastpaths	43
Appendix. Notices	45
Trademarks	46
Index	47

About this document

This document provides system administrators with conceptual and procedural information about how to set up, administer, and manage the AIX Network Data Administration Facility (NDAF) subsystem. Information about projects, policies, and data aggregation is included.

How to use this document

This document is organized to provide overview information, tasks, and conceptual details for the elements of the AIX Network Data Administration Facility subsystem.

Highlighting

The following highlighting conventions are used in this book:

Bold	Identifies commands, subroutines, keywords, files, structures, directories, and other items whose names are predefined by the system. Also identifies graphical objects such as buttons, labels, and icons that the user selects.
<i>Italics</i>	Identifies parameters whose actual names or values are to be supplied by the user.
Monospace	Identifies examples of specific data values, examples of text similar to what you might see displayed, examples of portions of program code similar to what you might write as a programmer, messages from the system, or information you should actually type.

Case-sensitivity in AIX

Everything in the AIX operating system is case-sensitive, which means that it distinguishes between uppercase and lowercase letters. For example, you can use the **ls** command to list files. If you type `LS`, the system responds that the command is not found. Likewise, **FILEA**, **FiLea**, and **filea** are three distinct file names, even if they reside in the same directory. To avoid causing undesirable actions to be performed, always ensure that you use the correct case.

ISO 9000

ISO 9000 registered quality systems were used in the development and manufacturing of this product.

The AIX Network Data Administration Facility

The AIX[®] Network Data Administration Facility (NDAF) subsystem provides for the secure centralized management of filesystem data relationships across a collection of systems. Its primary purpose is to facilitate the provisioning of data on Network File System version 4 (NFSv4) servers and the creation of a single NFSv4-exported file namespace that spans multiple server systems. NDAF is an entire system consisting of a set of NFS servers federated and managed as a single system.

NDAF concepts

The AIX Network Data Administration Facility (NDAF) is an AIX solution for centralized creation, placement, replication, ongoing management, and namespace federation of filesystem data across a network of machines.

Its primary purpose is to facilitate the provisioning of data on NFS version 4 (NFSv4) servers and the creation of a single NFSv4 exported file namespace that spans multiple server systems.

NDAF consists of several components. They include a domain where the network servers reside, a centralized server that controls the collection of data servers, and a directory tree of filesystem objects for management purposes.

Physical filesystem

A physical filesystem (PFS) is a filesystem that can access attached disk storage on a system and can be exported by an NFS server.

NDAF domain

An NDAF domain consists of one or more administration clients (that is, systems from which an administrator can control the NDAF environment through the **dmf** command), one or more AIX NDAF-enabled NFS servers, and potentially, one or more non-NDAF enabled NFS servers grouped around an NDAF administration server.

All systems in the NDAF domain share the same user and group definitions. For example, if NDAF is deployed using Kerberos security, all systems in the domain are members of the same Kerberos realm. The NDAF domain and the NFSv4 domain must be the same domain.

In an NDAF domain, the NDAF administration server receives its process information from commands run by one or more system administrators over a command-line interface (CLI). The NDAF administration server initiates all NDAF actions at the NFS data server systems that are part of the domain.

Data set

The basic unit of NDAF management is a *data set*. A data set is a directory tree. NDAF creates data sets and manages their attributes, mounting, and contained data.

Data sets, also called *dsets*, are manageable units of data that can be shared across a network. They provide basic management for replicating network data and inserting it into a namespace. They are linked together using data set references to form the file namespace. NDAF supports thousands of data sets or replicas across all managed servers. Read-only replicas of a data set can be created, distributed, and maintained across multiple data servers. When the master source for a collection of replicas is modified, the **dmf update replica** command is used to propagate the changes to all replica locations. A given data set can have as many as 24 replicas.

Data that is copied into data set directories is NFS-exported, but the data is not visible until the data set is mounted with the **dmf mount dset** command. Filesystem objects in a data set include files, directories, access control lists (ACLs), links, and more.

Unless specified when they are created, data sets are created in the directory specified when the **dms** daemon is started by the **-ndaf_dataset_default** parameter or, if unspecified, the **-ndaf_dir** parameter.

Cell

Data sets can be grouped with other data sets and organized into a single file namespace. This grouping is called a *cell*.

A cell is a unit of management and namespace that is hosted by an administration server. After a cell is defined on an administration server, more data sets can be created on that server using that cell. Each cell in an administration server is independent of all other cells hosted by that administration server. A cell contains its own namespace, consisting of data sets, and its own role-based security objects. Roles are privileges attached to a set of users that manage the resources within a cell. As many as eight distinct roles can be defined for each cell.

After a cell is created using the **dmf create cell name** command, it is automatically placed on the administration server. You cannot use the **dmf place cell name** to place a cell on the administration server. *Placing* a cell results in the transfer of the cell's root directory information from the administration server to the targeted data server. A cell can place its data sets on any server defined for the administration server on which the cell is hosted. NFSv4 clients mount the root directory of the cell to access the cell's full namespace.

All NFSv4 clients can view the objects within a cell by mounting the root of the cell from any NDAF server on which the cell has been placed.

NDAF supports up to 64 cells for every deployed NDAF instance (domain) that has cells residing on one or more data servers. When a cell is destroyed, all its data sets and replicas are also destroyed.

Replicas

Read-only copies of data sets can be created, distributed, and maintained safely across multiple data servers.

These read-only data sets are called *replicas*. A replica is placed in the global namespace in the same way as a data set. Multiple replicas of the same data set can be placed on different servers so that if the primary server of a replica becomes unavailable to the client, the client can automatically access the same files from a different server. Replicas will not reflect updates that are made to the data set unless the replica is updated using the **dmf update replica** command.

A given data set can have as many as 24 replicas.

Unless specified when they are created, replicas are created in the directory specified when the **dms** daemon is started by the **-ndaf_replica_default** parameter or, if unspecified, the **-ndaf_dir** parameter.

Master replica location

The master replication location is the place where the replica was first created, and it is the first location updated on any **update** action request. The other replica locations are updated afterwards asynchronously.

You can change the master location to another replica location using the **master** action request.

A master replica can never be unplaced before another master replica location is defined as a replacement for the first location.

Replica clones

For replicas, the **dmf place replica** command creates a clone of the replica at a specified location on the server.

If the replica is mounted in the cell, this clone location is added to the NFS replica list that is returned to the NFS clients that are accessing the replica. For more information, see NFS replication and global namespace. The order of the referrals in this list depends on the network configuration. Every clone location of a replica is updated asynchronously upon **dmf update** commands. The **dmf place replica** command takes as parameters the server and, optionally, the local path on the server.

A clone location of a replica can be removed from a server, as in the following example:

```
dmf unplace replica my_server local_path -a my_admin -c my_cell -o my_replica
```

In this example, `my_server` is the name of the server on which the clone resides and `my_replica` is the name of the replica. The clone location is unexported, and its content is destroyed. This location is also removed from the filesystems locations data list returned by NFSv4 for this replica in the cell. The other locations of the replica remain the same. The **dmf update replica** command updates clones along with their original replicas to be refreshed with the content of the original source data set.

Replication updates

The master replica is a read-only copy of the source data set, and the clones are copies of the master replica. If the source data set is updated, the replicas are not updated until explicitly done so using the **dmf update replica** command.

There are two methods of data transfer:

copy method

performs data transfer using full file tree copy. The copy method implements the data transfer method plugin interface and performs a data transfer operation by doing a complete walk of the directory tree for the data set and transmitting all objects and data to the target.

rsync method

performs data transfer using rsync-like algorithm. The rsync method performs a data transfer operation by doing a complete walk of the directory tree for the data set and transmitting only deltas for directories and data to the target. It is beneficial when updating replicas because it only sends changed blocks of information, so it reduces network bandwidth considerably.

Administration client

An administration client is any system in the network that has the **ndaf.base.client** fileset installed on it from which the **dmf** command can be run.

The NDAF administration server receives its process information from commands run by system administrators over a command-line interface. The program name for this administration client is the **dmf** command.

Related concepts

“dmf” on page 5

In NDAF command strings, **dmf** is the prefix for all command-line interface commands.

Administration server

The NDAF administration server is a data server that runs daemon processes and acts as the central point of control for the collection of NDAF data servers.

It receives commands from the system administrators who use the administration client (the **dmf** command), the **dms** command, and the **dmadm** command. The NDAF administration server maintains a master database of configuration information and sends commands to the data servers. When a loss of

communication occurs between the administration server and the data servers, the NDAF-managed data already present on the data server can still be accessed. After network connectivity is restored, the transactions between the systems are eventually completed.

The administration server is configured before all other NDAF components. This server requires 64-bit systems running the AIX 64-bit kernel.

Administration server databases are created in an **admin** subdirectory in the directory specified by the **-ndaf_dir** parameter when the **dmadm** daemon is started.

Data server

A data server is the server that runs the daemon process (the **dms** daemon) controlling an NFS file server and its associated physical filesystem (PFS). The data provisioned with NDAF resides at the data server.

The **dms** process runs at each data server and carries out actions in underlying filesystems. It sets default directories, timeout values, level of logging, security method used, Kerberos keytab path, Kerberos principal, and communication ports on each data server. Only data servers within the NDAF domain can be replicated.

Data server databases are created in a **server** subdirectory in the directory specified by the **-ndaf_dir** parameter when the **dms** daemon is started. These servers require 64-bit systems running the AIX 64-bit kernel. The administration server also serves as a data server.

Principal

A principal is an authorized NDAF user that Kerberos and other security methods screen for during security checks.

Principals control how objects can be manipulated and by which operations.

Only the first user to run the **dmf create admin** command, called the **DmPrincipal**, can create cells, servers, and roles. Additional NDAF principals can be added to manage an object with the **dmf add_to object DmPrincipal=login** command. All members of the **DmPrincipal** list are considered to be owners of the object and can control it.

NDAF principals can also be removed using the **dmf remove_from** action.

Graphical representation of an NDAF domain

The basic concepts of the functioning objects of an NDAF domain can be depicted graphically.

The following figure shows the organization of various objects within NDAF:




Figure 1. The NDAF domain

NDAF commands

The four primary commands that NDAF uses to perform its operations are the **dmf** command, **dms** command, **dmadm** command, and the **dms_enable_fs** command.

For more information about other NDAF commands, refer to “Additional NDAF command processes” on page 41.

dmf

In NDAF command strings, **dmf** is the prefix for all command-line interface commands.

These command strings follow a consistent structure: the actual name of the executable (**dmf**), an action request called a *verb* (such as **create** or **delete**), the object to which the action is being applied (such as a server or a cell), and any subsequent parameters (such as *names*). These parameters are position-dependent.

The **dmf** command can be run on 32-bit or 64-bit systems.

dmadm

The **dmadm** command operates NDAF on the administration server.

Both the **dmadm** and **dms** commands are required services on the administration server’s Kerberos keytab. The **dms** processes must be launched along with the **dmadm** daemons for the administration machine to function correctly.

Related information

dmadm Command

Provides complete information on the **dmadm** command.

dms

The **dms** command operates NDAF on a data server.

On a data server within an NDAF domain, the **dms** command sets default directories, timeout values, level of logging, security method used, Kerberos keytab path, Kerberos principal, and communication ports.

Related information

dms Command

Provides complete information on the **dms** command.

dms_enable_fs

The **dms_enable_fs** command enables, disables, or queries the capability to create cells, data sets, and replicas on a filesystem.

Related information

dms_enable_fs Command

Provides complete information on the **dms_enable_fs** command.

NDAF deployment models

NDAF is designed to be deployed in either a data center environment or a wide area network (WAN) environment where servers are separated by distance or less reliable networks.

Deployments combining the two aspects are also possible. Each has unique considerations.

Data centers

Fast reliable networks are typical of data center environments. Data center configurations usually ensure a high degree of trust between the systems and the data flowing between them.

With fast reliable networks, replication of larger data sets with more maintained copies is possible. Networks in data center environments can handle replication of data that changes more frequently or changes more extensively.

Depending on the security of a data center environment, NDAF can be deployed without Kerberos-based authentication or the use of the Kerberos-based data protection features.

Wide area networks

In a wide area network (WAN) environment, network bandwidth or reliability constraints can limit the size of data that can be reasonably replicated across systems. The frequency and amount of change to data becomes an important consideration when deciding whether or not to replicate it, how many copies to maintain, and how often to schedule replica updates. These considerations must be balanced against the benefit of placing the data at remote locations to get it closer to the point of consumption for better performance and increased availability.

NDAF is designed so that the loss of communication between the administration and data servers does not prevent access to NDAF-managed data already present on the data server. It is also designed to eventually complete transactions between systems after network connectivity is restored.

For this deployment model, the use of Kerberos-based security is preferable for providing trusted authentication or protection of data on the network.

NDAF security

NDAF systems, including the point of administration, can use strong security based on Kerberos and open network computing (ONC) remote procedure call (RPC) with RPCSEC-GSS for authentication when communicating with each other.

RPCSEC_GSS is a security method that can optionally be applied to ONC RPC. RPCSEC-GSS is a protocol that applies Generic Security Services (GSS) to RPC.

Security for NFS file access

To manage access to NFS clients, the NFSv4 access control list (ACL) method can be used for directories containing data sets, at filesystem level, and on the mounting point (`nfsroot`) of each server.

Filesystem objects are typically associated with an ACL that (for NFSv4 ACLs as opposed to AIX ACLs) consists of a series of access control entries (ACEs). Each ACE defines an identity and its related access rights.

Access control consists of protected information resources that specify who can be granted access to those resources. The operating system offers a choice of need-to-know or discretionary security. The owner of an information resource can grant other users read- or write-access rights for the resource. A user who is granted access rights to a resource can transfer those rights to other users. This security permits user-controlled information flow in the system; the owner of an information resource defines the access permissions to that resource.

Users have user-based access only to the objects that they own. Typically, users receive either the group permissions or the default permissions for a resource. The major task in administering access control is to define the group memberships of users, because these memberships determine the users' access rights to the files that they do not own.

The NFSv4 ACL type provides fine-grained control over access rights and also provides for features such as inheritance. NFSv4 ACLs consist of an array of ACEs. Each ACE defines access rights for an identity.

In AIX, use the **aclget**, **acledit**, **aclput** and **aclconvert** commands to manage NFSv4 ACLs. Additional information on AIX support of NFSv4 ACLs can be found in the Access Control List section of *Security*.

Exporting with Kerberos

By default, the data servers only export filesystems for NFSv4 access with all security types allowed.

You might want to change the default export options to restrict the **auth_sys** security mechanism or to permit NFS version 3 mounts.

To do this, run **chndaf** command with the following arguments:

```
chndaf -nfs_args=<new nfs args>
```

Format the *new nfs args* exactly as they would be for the **exportfs** command.

For example, to restrict exports to krb5p only, run `chndaf -nfs_args=sec=krb5p`.

If you specify the **vers=** stanza, you *must* include 4 (see below); NDAF will not work correctly otherwise. If you do not specify the **vers=** stanza, the filesystems will be exported for NFSv4 only.

To export for versions 3 and 4, run `chndaf -nfs_args=vers=3:4`.

For more information about Kerberos and RPCSEC-GSS security, see *Setting up a network for RPCSEC-GSS*.

Roles

Roles are privileges attached to a set of NDAF principals for managing the resources within a cell. NDAF roles are a distinct function separate from AIX administrative roles.

NDAF principals match Kerberos principals when using the Kerberos authentication, and they match user names when using system-based authentication (such as the **auth_sys** security mechanism).

At first, only the **DmPrincipal** attribute (signifying the first user to run the **dmf create admin** command) can create cells, servers, and roles. Additional NDAF principals can be used to manage an object with the **dmf add_to object DmPrincipal=login** command. All members of the **DmPrincipal** list are considered to be owners of the object and can control it.

NDAF principals can also be removed using the **dmf remove_from** action.

Creating a role and assigning it to a user on the **DmMember** list defines a set of command capabilities that are granted to the users of that role. The following capabilities are included:

Note: Each of these capabilities can be set to either 0 or 1. The default for each of these capabilities is 1.

DmCreatedDs

If nonzero, specifies that this role permits data set creation on the servers listed in the **DmServer** list of the role. An asterisk (*) signifies that data set creation is permitted on every server that is part of the list. This applies in the same line to replicas, except that with replicas, the user also must be permitted to duplicate the source data set. This can be done if the user is a **DmPrincipal** of the source data set, or if the user is a **DmMember** of a role that is part of the **DmOwningRole** of the source data set and the role has its **DmDuplicateDs** field set to 1.

DmDestroyDs

If nonzero, specifies that this role permits data set destruction if this role is listed in the **DmOwningRole** of the data set. It applies in the same line to replicas.

DmModifyDs

If nonzero, specifies that this role permits data set or replica modification for the data sets and replicas that have this role in their **DmOwningRole** list. Modification involves using the following commands:

- **dmf set** command for the data set or replica
- **dmf add_to** command and **dmf remove_from** command for the data set or replica
- **dmf place** command and **dmf unplace** command for the replica if it is placed on (or unplaced from) a server that is listed in the **DmServer** list of that role
- **dmf mount** command and **dmf unmount** command for the data set or replica if it is directly mounted in the cell, or if it is mounted within another data set and this data set has a role in its **DmOwningRole** list with this user as a **DmMember**, and the **DmModifyDs** is set to 1

DmDuplicateDs

If nonzero, specifies that this role permits data set replication of the data sets that have this role in their **DmOwningRole** list.

DmCreateRole

If nonzero, specifies that this role permits role creation.

DmDestroyRole

If nonzero, specifies that this role permits role destruction for the roles that have this role in their **DmOwningRole** list.

DmModifyRole

If nonzero, specifies that this role permits role modification (**dmf set**, **dmf add_to**, and **dmf remove_from**) for the roles that have this role in their **DmOwningRole** list.

Roles can also be defined using the System Management Interface Tool (SMIT). For more information on creating roles, refer to “Creating and managing roles” on page 17.

After they are created using the **dmf create role** command, roles apply to every server by default (specified by an asterisk [*] in the **DmServer** list). They can then be applied on selected servers so that data sets or replicas can be created and placed using the **dmf add_to role DmServer=name** command, and afterwards using a **dmf remove_from role Dmserver=*** command. A role can also be applied to a single data set or replica using the **dmf add_to DmOwningRole** command on this data set or replica.

NDAF installation and configuration

You can install and configure NDAF.

Installing NDAF

Use SMIT (fastpath: **smitty install_all**) or the **installp** command to install the **ndaf.base** fileset. If the recommended Kerberos 5 security is required, install the **krb5.client** fileset.

To install NDAF, the system must have IBM AIX 5L Version 5.3 with the 5300-05 Technology Level or greater installed. The system must be using the 64-bit kernel.

A given system can assume one of three roles in an NDAF domain. Different pieces of the **ndaf.base** fileset must be installed depending on the roles. The roles are:

Administration server

For this system, **ndaf.base.admin** and **ndaf.base.server** must be installed. There is only one administration server for a federation of servers.

Data servers

For these systems, **ndaf.base.server** must be installed.

Administration clients

For these systems, only **ndaf.base.client** must be installed.

For information about the command and flags, see the **installp** command in *AIX 5L Version 5.3 Commands Reference*.

Note: By default, the NDAF daemons are not started after installing the package. They are also not configured to be started automatically on the next boot. For instructions on starting the daemons, see “Configuring an NDAF data server” on page 11 or “Configuring the NDAF administration server” on page 12.

Configuring NFS version 4

NDAF servers must be configured as NFSv4 servers.

To configure an NDAF server as an NFSv4 server:

1. Set the NFSv4 domain name with the **chnfsdom** command.
2. Start the **nfsrgyd** daemon with the following command:

```
startsrc -s nfsrgyd
```
3. Ensure that **nfsd** and **rpc.mountd** are automatically started on system boot. The simplest way to do this is to use the **touch** command to touch the **/etc/exports** file.
4. To enable aliasing, create or choose a directory on the server and set the NFSv4 root location with the **chnfs -r** command. For example, enter the command **chnfs -r /ndaf** (where **/ndaf** is a directory on the server). NDAF uses the **exname exportfs** option to create the global namespace using aliasing. Alias and non-alias exports cannot be mixed, so if the NDAF server is already an NFS server without an NFS root, the administrator is not able to set the root, and NDAF will not function properly. All

current exports must be unexported before the root can be set, and all future exports must be aliased to appear under the NFS root. For more information, refer to */etc/exports* in *AIX 5L Version 5.3 Files Reference*.

5. Enable NFSv4 server replicas, aliasing, and referrals with the **chnfs -R on** command.

Result: NFSv4 is configured.

Configuring Kerberos 5

The NDAF administration server and all NDAF data servers and administration clients must be configured as Kerberos clients.

Note: A full discussion of Kerberos 5 configuration is beyond the scope of this topic. This topic is meant to describe the Kerberos principals needed by the NDAF product. For detailed instructions on setting up Kerberos, refer to the *IBM Network Authentication Service Version 1.4 Administrator's and User's Guide*, which is installed in the following directories:

HTML /usr/lpp/krb5/doc/html/language/ADMINGD

PDF /usr/lpp/krb5/doc/pdf/language/ADMINGD

In order to access these files, **krb5.doc** must be installed.

You can configure the NDAF administration server and all NDAF data servers and administration clients as Kerberos clients with either the **config.krb5** command or the **mkkrb5clnt** command. (The appropriate command depends on how Kerberos will be used on this system.) If you want an integrated login, you can use the **mkkrb5clnt** command to manage the integrated login configuration.

The Kerberos administrator must establish Kerberos service principals for every data server and for the administration server. The following principals are required:

Administration clients

Every administration client must have a service principal in the form of *dmf/fully-qualified domain name*.

Data servers

Every data server (including the administration server) must have a service principal in the form of *dms/fully-qualified domain name*.

Administration server

The administration server must have a service principal in both of the following forms:

- *dmadm/fully-qualified domain name*
- *dms/fully-qualified domain name*

Any NFS or data server that exports for Kerberos

Any NFS or data server that exports for Kerberos must have a service principal in the form of *nfs/fully-qualified domain name*.

The administrator can create these Kerberos service principals with the **add_principal** command under the Kerberos administration (**kadmin**) command (**/usr/sbin/krb5/kadmin**). The administrator must then add the server's service principals to the server's keytab file. You can do this with the **ktutil** command. For example:

```
ktutil: addent -password -p dms/test.austin.ibm.com -k 1 -e des
ktutil: wkt /etc/krb5/krb5.keytab
```

where the key version number (kvno) (-k) and encryption types are set as appropriate. All NDAF administrators must be known as Kerberos 5 users if Kerberos 5 security is used.

RPC port requirements

In order to communicate correctly, each server must be aware of the ports the other servers are listening on and emitting to.

The sending and receiving ports between communicating servers must have identical values.

Ports basically work by pairs. For example:

- The data server connects to another data server's SSP port, and the other data server listens to SSP (28003 is the default port).
- The data server connects to the administration server ACP, and the administration server listens to ACP (28002 is the default port).
- The administration server connects to a data server SP port, and the data server listens to SP (28001 is the default port).
- A client connects to the administration server AP, and the administration server listens to AP (28000 is the default port).

Note: When you start a server with non-default ports, make sure that the other servers are started with the same values for the specified non-default ports.

Configuring an NDAF data server

The primary configuration for an NDAF data server involves starting the **dms** daemon.

This can be accomplished using the System Management Interface Tool (SMIT) menus (fastpath **ndaf**) or directly using the **mkndaf** and **chndaf** commands. Both methods will update the **/etc/rc.ndaf** startup file for simple (and if needed, automatic) restart on reboot. Due to the aliasing used to create the global namespace, the view from an NFS client is different than the local view from an NDAF data server. The view from an NFSv4 client mounting an NDAF data server's root is:

```
/mount point/cell name/dset mount name
```

The actual path to the data-set data on the data server (if not specified when the data set is created) is:

```
/ndaf_dataset_default/dset/ndaf_assigned_dir_name
```

Similarly, the path to replica data on the data server (if not specified when the data set is created) is:

```
/ndaf_replica_default/replica/ndaf_assigned_dir_name
```

There are three key considerations when starting NDAF on a data server:

Where should data sets and replicas reside by default?

Unless specified when a data set or replica is created, the data set or replica is created in the directory specified when the **dms** daemon starts. These directories must reside in a filesystem that has been enabled for data sets using the **dms_enable_fs** command, and should be large enough for the expected size of the data sets and replicas. It is recommended that this filesystem be a separate, dedicated filesystem created specifically for storing data sets and replicas.

Note: The **/**, **/tmp**, and **/proc** filesystems cannot be enabled for data sets.

Where should NDAF log and state data reside?

The directory specified will have "log" and "server" subdirectories that contain data crucial to the operation of the NDAF data server. These subdirectories do not need to reside in a fileset enabled for data sets. The data in the "server" subdirectory must be backed up along with the data-set data for data recovery purposes.

What type of security will be used?

The **auth_sys** security type provides a level of security appropriate only within a trusted data center, whereas Kerberos can be used where stronger security is required.

There are three levels of Kerberos security:

- krb5** Performs authentication, verifying that the message was sent by who it claims sent it.
- krb5i** Performs checksum operations to verify the integrity of the data. Integrity promises that the message has not been modified (and provides authentication).
- krb5p** Encrypts the data. Privacy prevents the message from being read by anyone but the intended recipient (and provides authentication and integrity).

For example, a data server could be configured with the following steps. (This example assumes NFS has been configured as described in “Configuring NFS version 4” on page 9).

```
# Enable the filesystem where data sets and replicas will go

dms_enable_fs -s /ndafpool

# Configure default dirs and security

chndaf -ndaf_dir=/var/dmf -ndaf_dataset_default=/ndafpool \
-ndaf_replica_default=/ndafpool -security=auth_sys

# Start the dms daemon (and add to inittab so will start on reboot)

mkndaf
```

Configuring the NDAF administration server

When configuring NDAF, you must first configure the administration server. There is one NDAF administration server for a given federation of NDAF data servers.

The NDAF administration server is the central point of control and all NDAF administration requests from NDAF clients are handled on this server. The administration server is also a data server, so the configuration procedure in “Configuring an NDAF data server” on page 11 also applies to the administration server. To configure the administration server, you must also configure the system as a data server. In addition to “log” and “server” subdirectories, there will also be an “admin” subdirectory. The only additional configuration step is to use the **chndaf** command to start the **dmadm** daemon as well as the **dms** daemon:

```
chndaf -admin_serv=yes
```

Configuring an NDAF administration client

An NDAF administration client is any system that is used to run data-management commands that are handled by the NDAF administration server.

There is no configuration necessary on the administration client beyond installing the **ndaf.base.client** files. The **dmf** command or NDAF Management SMIT menus are used for NDAF administration.

Managing NDAF

You must add the NDAF server and the data servers before you can perform other NDAF management tasks. You can then create and manage cells, roles, data sets, and replicas; populate data sets; construct cell namespaces; and federate servers without the NDAF into an NDAF environment.

Adding servers for NDAF

You must add the NDAF administration server and all of the data servers to the system before you can perform any other NDAF management tasks.

You can use the **dmf** command to add the NDAF administration server:

```
dmf create admin name [-r] [-a admin_server]
```

where:

-a *admin_server*

Specifies the Domain Name System (DNS) name or IP address of the administration server. The port can be added using a colon separator.

name Specifies the name for the administration server to be created.

-r Prints the universally unique identifier (**uuid**) assigned to the request.

Note: Entering `dmf create admin my_admin` also creates the **my_admin** server object.

You can use the **dmf** command to add a data server:

```
dmf create server name dns_target [-e] [-r] [-a admin_server]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

dns_target

Specifies the DNS name or IP address of the server. The port can be added using a colon separator.

-e Specifies that the object is external to NDAF.

name Specifies the name for the data server to be created.

-r Prints the **uuid** assigned to the request.

To add the NDAF administration server using SMIT, perform the following steps:

1. From the **NDAF** menu, select **NDAF Management** → **Administration Server Management** → **Create Admin Server**.

Note: You can also use the **ndafadmincreate** fastpath.

2. Specify the DNS name or IP address of the administration server in the **Admin Server DNS name** field and press Enter.
3. Specify a name for the new administration server in the **Admin Server name** field and press Enter.

To add an NDAF data server using SMIT, perform the following steps:

1. From the **NDAF** menu, select **NDAF Management** → **Data Server Management** → **Create Data Server**.

Note: You can also use the **ndafdscreate** fastpath.

2. Specify the DNS name or IP address of the administration server in the **Admin Server DNS name** field.
3. Specify a name for the new data server in the **Data Server name** field and press Enter.
4. Specify the DNS name or IP address of the new data server in the **Data Server DNS name** field and press Enter.

Creating and managing cells

A *cell* is a collection of data sets organized into a single file namespace for use with NFSv4 servers. NFSv4 clients are expected to mount the root directory of the cell to access the cell's full namespace.

Creating a cell

You can create a cell for use with NFSv4 servers.

You must create an NDAF administration server before you can create a cell.

You can use the **dmf** command to create a cell:

```
dmf create cell name [-w timeout] [-r] [-a admin_server]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator

name Specifies the name for the cell to be created.

-r Prints the **uuid** assigned to the request.

-w *timeout*

Specifies how long the command can wait before completing.

Perform the following steps to create a cell using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Namespace (cell) Management** → **Create cell namespace**.

Note: You can also use the **ndafcellcreate** fastpath.

2. Specify the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field.
3. Enter a name for the new cell in the **Cell name** field and press Enter.

To create a cell named **cell1** in the NDAF domain that is managed by the **NDAFServer1** administration server, perform the following steps:

1. From the **NDAF** menu, select **NDAF Management** → **Namespace (cell) Management** → **Create cell namespace**.
2. Enter NDAFServer1 in the **Admin name** field.
3. Enter cell1 in the **Cell name** field and press Enter.

Listing cell namespaces

You can list the cells that have been defined for a specified administration server.

You can use the **dmf** command to list cells:

```
dmf enumerate admin cell [pattern] [-r] [-a admin_server]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

pattern

Optional matching text pattern. Valid values include ? and *.

-r Prints the **uuid** assigned to the request.

Perform the following steps to lists cells using SMIT:

1. Select **NDAF** → **NDAF Management** → **Namespace (cell) Management** → **List Cell Namespaces**.

2. Specify the name of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.

Showing and changing cell attributes

You can show the attributes of a specified cell. You can modify some of these attributes if you have the necessary authorization.

You must have the required authorization to modify the attributes for a cell.

You can use the **dmf** command to show the attributes for a cell:

```
dmf show cell [-r] [-a admin_server] [-c container]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name this command is addressed to.

-r Prints the **uuid** assigned to the request.

You can use the **dmf** command to change the attributes for a cell:

```
dmf set cell key=value [-r] [-a admin_server] [-c container]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name this command is addressed to.

key=value

Specifies an attribute and the value to assign to it. Valid keys are **DmLogLevel** and **DmLocsMax**.

-r Prints the **uuid** assigned to the request.

Perform the following steps to show and change the attributes for a specific cell using SMIT:

1. Select **NDAF** → **NDAF Management** → **Namespace (cell) Management** → **Change/show cell attributes** .
2. Specify the name of the administration server that manages the NDAF domain in the **Admin name** field.
3. Enter the name of the cell in the **Cell name** field (or choose one from the list by pressing F4). The following attributes are displayed:

Admin server DNS name (or IP address)

Specifies the DNS name or IP address of the administration server that manages the NDAF domain

Admin server name

Specifies the name of the administration server that manages the NDAF domain

Cell name

Specifies the name of the cell

Cell UUID

Specifies the **uuid** for the cell

Maximum number of reported locations

Specifies the maximum number of NFS location referrals that can be returned to an NFS client for an object

NDAF principals

Enter the list of users, separated by commas, directly in the input field. Users from this list are owners of this cell and can manipulate the cell

Removing a cell namespace

You can remove a cell object and clean the databases of all the objects that have been defined within the cell.

You can use the **dmf** command to remove a cell namespace:

```
dmf destroy cell [-r] [-f] [-a admin_server] [-c container]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the container (that is, the cell name).

-f Forces the action without confirmation.

-r Prints the **uuid** assigned to the request.

Perform the following steps to remove a cell namespace using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Namespace (cell) Management** → **Remove cell namespace**.
2. Specify the name of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell to be removed in the **Cell name** field and press Enter. A standard SMIT dialog box displays to confirm the destruction of the cell.

Adding a server to a cell namespace

A cell can use a data server to host the cell's data set.

You can use the **dmf** command to enable a cell to use a data server to host the cell's data set:

```
dmf place cell server_name [-r] [-a admin_server] [-c container]
```

where:

server_name

Specifies the server on which the cell should be made available for mounting by NFS.

-r Prints the **uuid** assigned to the request.

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

Perform the following steps to enable a cell to use a data server to host the cell's data set using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Namespace (cell) Management** → **Add Server to a Cell Namespace**.

2. Specify the name of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell Name** field (or choose one from the list by pressing F4) and press Enter.
4. Enter the name of the data server in the **Data server name** field (or choose one from the list by pressing F4) and press Enter.

Removing a server from a cell namespace

You can prevent a cell from using a data server to host the cell's data sets.

You can use the **dmf** command to prevent a cell from using a data server to host the cell's data sets:

```
dmf unplace cell server_name [-r] [-f] [-a admin_server] [-c container]
```

where:

server_name

Specifies the server on which the cell should become unavailable for mounting by NFS.

-r Prints the **uuid** assigned to the request.

-f Forces the action without confirmation.

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

Perform the following steps to prevent a cell from using a data server to host the cell's data sets using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Namespace (cell) Management** → **Remove Server from a Cell Namespace**.
2. Specify the name of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell Name** field (or choose one from the list by pressing F4) and press Enter.
4. Enter the name of the data server in the **Data server name** field (or choose one from the list by pressing F4) and press Enter.

Creating and managing roles

A *role* is a set of privileges associated with a set of users. Roles are used to manage resources within a cell. Administrators can create, list, remove, validate and change the options of roles.

Creating a role

You can create a role. A *role* is a set of privileges associated with a set of users. Roles are created for cells and are used to manage resources within a cell.

You must create a cell before you can create a role.

You can use the **dmf** command to create a role:

```
dmf create role name [-r] [-a admin_server] [-c container]
```

where:

- a *admin_server***
Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.
- c *container***
Specifies the cell name.
- name* Specifies the name of the role to be created.
- r** Prints the **uuid** assigned to the request.

Perform the following steps to create a role using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Delegation of administration rights** → **Create a role**.
2. Enter the DNS name or the IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell name** field (or choose one from the list by pressing F4).
4. Enter the name of the role to be created in the **Role name** field and press Enter.

Showing and changing role attributes

You can show the attributes for a specific role. If you have the required privileges, you can modify some role attributes.

You can use the **dmf** command to show the attributes for a role:

```
dmf show role [-r] [-a admin_server] [-c container] [-o object]
```

where:

- a *admin_server***
Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.
- c *container***
Specifies the cell name.
- o *object***
Specifies the name of the object this command is addressed to.
- r** Prints the **uuid** assigned to the request.

You can use the **dmf** command to change the attributes for a role:

```
dmf set role key=value [-r] [-a admin_server] [-c container] [-o object]
```

where:

- a *admin_server***
Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.
- c *container***
Specifies the cell name.
- key=value*
Specifies an attribute and the value to assign to it. Valid keys are **DmCreateDs**, **DmDestroyDs**, **DmModifyDs**, **DmDuplicateDs**, **DmCreateRole**, **DmDestroyRole**, and **DmModifyRole**.
- o *object***
Specifies the name of the object this command is addressed to.
- r** Prints the **uuid** assigned to the request.

Perform the following steps to show and change the attributes for a role using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Delegation of administration rights** → **Change / show role options**.
2. In the dialog panel, enter the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell name** field (or choose one from the list by pressing F4) and press Enter.
4. In the dialog panel, enter the name of the role to be shown or modified in the **Role name** field (or choose one from the list by pressing F4) and press Enter. The following attributes are displayed:

Admin server DNS name (or IP address)

Specifies the DNS name or the IP address of the administration server.

Cell name

Specifies the name of the cell.

Role name

Specifies the name of the role.

Role UUID

Specifies the universal unique identifier of the role.

NDAF principals

Specifies the list of users (separated by commas) directly in the input field. These users are owners of this administration server and can manipulate the server.

Owning roles

Specifies the roles that can apply to an object.

Members

Specifies the principals that are members of this role (that is, the members for which this role permits administrative actions).

Servers

Specifies the servers for which this roles permits activity.

Dset creation right

Specifies whether the role has data set creation rights. The options are **yes** or **no**.

Dset destruction right

Specifies whether the role has data set destruction rights. The options are **yes** or **no**.

Dset modification right

Specifies whether the role has data set modification rights. The options are **yes** or **no**.

Dset duplication (replication) right

Grants the right to duplicate (replicate) a dset. The options are **yes** or **no**.

Role creation right

Specifies role creation rights. The options are **yes** or **no**.

Role destruction right

Specifies role destruction rights. The options are **yes** or **no**.

Role modification right

Specifies role modification rights. The options are **yes** or **no**.

Removing a role

You can remove a role.

You can use the **dmf** command to remove a role:

```
dmf destroy role [-r] [-f] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

-f Forces the action without confirmation.

-o *object*

Specifies the name of the object this command is addressed to.

-r Prints the **uuid** assigned to the request.

Perform the following steps to remove a role using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Delegation of administration rights** → **Remove role**.
2. Enter the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell name** field (or choose one from the list by pressing F4) and press Enter.
4. Enter the name of the role to be removed in the **Role name** field and press Enter. A confirmation dialog displays.

Listing roles

You can list all of the roles for a cell.

You can use the **dmf** command to list all of the roles for a specified cell:

```
dmf enumerate cell role [pattern] [-r] [-a admin_server] [-c container]
```

where:

pattern

Optional matching text pattern. Valid values include a question mark (?) and an asterisk (*).

-r Prints the **uuid** assigned to the request.

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

Perform the following steps to list all of the roles for a specified cell using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Delegation of administration rights** → **List roles**.
2. Enter the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell name in the **Cell name** field and press Enter.

Creating and managing data sets

A *data set* (dset) is a directory tree of filesystem objects (files, directories, ACLs, links, and so on).

You can create, remove, validate, list, mount, and unmount data sets and change their options.

Listing data sets

You can list all data sets for a specified cell or data server.

You can use the **dmf** command to list all data sets for a specified cell:

```
dmf enumerate cell dset [pattern] [-r] [-a admin_server] [-c container]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

pattern

Optional matching text pattern. Valid values include a question mark (?) and an asterisk (*).

-r Prints the **uuid** assigned to the request.

You can use the **dmf** command to list all data sets for a specified server:

```
dmf enumerate server dset [pattern] [-r] [-a admin_server] [-c container]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the server name.

pattern

Optional matching text pattern. Valid values include a question mark (?) and an asterisk (*).

-r Prints the **uuid** assigned to the request.

Perform the following steps to display the list of all data sets for a specified cell or administration server using SMIT:

1. From the **NDAF** menu, select **Data management** → **Dataset management** → **List datasets**.
2. Specify the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Select whether to list all data sets for a cell or for a server by choosing the appropriate option using F4 and then press Enter.
4. Enter the cell name or server name in the **Cell name** or **Data server Name** field and press Enter (use F4 to select a cell or a server from a list). Leave this field blank and press Enter to display all the data sets for all cells or all data servers.

Creating data sets

When you create a data set, you must specify an administration server, a namespace, and a data server.

You can use the **dmf** command to create a data set:

```
dmf create dset name server [path] [-r] [-a admin_server] [-c container]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c container

Specifies the cell name.

name Specifies the name for the data set to be created.

path Specifies the local path on the server. If the path parameter is omitted, the server puts the data set in its default pool.

-r Prints the **uuid** assigned to the request.

server Specifies the server name.

Perform the following steps to create a data set using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Dataset management** → **Create Dataset**.
2. Specify the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the cell name in the **Cell name** field (or choose one from the list by pressing F4).
4. Enter the data set name in the **Dset name** field.
5. Enter the data server name in the **data server name** field. Press Enter or define a local path in the following step.
6. Specify where on the server the data set will be created in the **Local path on the server** field and press Enter. If you do not specify a path, the new data set will be created on the default data set path defined for the server. The default data set path is the path specified when the **dms** daemon is started by the **-ndaf_dataset_default** parameter. If this parameter is not specified, the default path is **\$ndaf_dir/server/dsets**, where **\$ndaf_dir** is the path specified by the **-ndaf_dir** parameter. You can edit this path using the **dmf set DmDefaultDsetPath** command in the NDAF CLI.

Validating data sets

You can check the consistency of a data set in a specific namespace.

You can use the **dmf** command to validate a data set:

```
dmf validate dset [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a admin_server

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c container

Specifies the cell name.

-o object

Specifies the name of the object to which this command is addressed.

Perform the following steps to check for the existence of a data set in a specified namespace using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Dataset management** → **Check Dataset**.
2. Specify the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell name** field and press Enter.
4. Enter the name of the data set in the **Dset name** field (or choose one from the list by pressing F4) and press Enter.

Showing and changing data set attributes

You can show the attributes for a data set. If you have the required authorization, you can modify the attributes for a data set.

You can use the **dmf** command to show the attributes for a specified data set:

```
dmf show dset [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

-o *object*

Specifies the name of the object this command is addressed to.

-r

Prints the **uuid** assigned to the request.

You can use the **dmf** command to change the attributes for a specified data set:

```
dmf set dset key=value [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

key=value

Specifies an attribute and the value to assign to it. Valid keys are **DmOwner**, **DmGroup**, **DmMode**, and **DmLocsMax**.

-o *object*

Specifies the name of the object this command is addressed to.

-r

Prints the **uuid** assigned to the request.

You can use the **dmf** command to add a key/value item to a list-based attribute for a data set:

```
dmf add_to dset key=value [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

key=value

Specifies an attribute and the value to assign to it. Valid keys are **DmPrincipal**, **DmOwningRole**, and **DmTransferTable**.

-o *object*

Specifies the name of the object this command is addressed to.

-r

Prints the **uuid** assigned to the request.

You can use the **dmf** command to remove a key/value item from a list-based attribute for a data set:

```
dmf remove_from dset key=value [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

key=value

Specifies an attribute and the value to assign to it. Valid keys are **DmPrincipal**, **DmOwningRole**, and **DmTransferTable**.

-o *object*

Specifies the name of the object this command is addressed to.

-r

Prints the **uuid** assigned to the request.

Perform the following steps to show or change the attributes for a specified data set using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Dataset management** → **Change / show Dataset attributes**.
2. Specify the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin server name** field.
3. Enter the name of the cell in the **Cell name** field (or choose one from the list by pressing F4).
4. Enter the name of the data set in the **Dset name** field. The following attributes are displayed:

Admin server DNS name (or IP address)

Specifies the DNS name or IP address of the administration server.

Cell name

Specifies the name of the cell.

Dset name

Specifies the data set name.

Dset UUID

Specifies the universal unique identifier for this data set.

Version

Specifies the version of the replica data set.

Owner

Specifies the owner that should be set in the filesystem for this data set.

Group

Specifies the group that should be set in the filesystem for this data set.

Mode

Specifies the mode that should be set in the filesystem for this data set. Permissible values are 000 through 777 octal (in other words, the value is a normal UNIX[®] file permission setting).

Maximum number of reported locations

Specifies the maximum number of NFS locations referrals that can be returned to an NFS client for an object.

NDAF principals

Specify a list of users (separated by commas) directly in the input field. Users from this list will own this data set and can manipulate the data set.

Owning roles

Specifies the roles that can manage this data set.

Transfer methods

Specifies the method this data server will use for data transfer (or choose one from the list by pressing F4). This field accepts multiple, comma-separated values. Possible values are **copy**, **rsync**, **copy + rsync**. The default value is **copy**.

Showing data set locations

You can display the physical locations of a data set.

You can use the **dmf** command to display the physical locations of a specified data set:

```
dmf show dset [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

-o *object*

Specifies the name of the object this command is addressed to.

-r Prints the **uuid** assigned to the request.

Perform the following steps to display the physical locations of a specified data set using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Dataset management** → **Show Dataset locations**.
2. Specify the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin server name** field.
3. Enter the name of the cell in the **Cell name** field.
4. Enter the name of the data set in the **Dset name** field (or choose one from the list by pressing F4) and press Enter. The data set attributes and data set locations are displayed.

Removing data sets

You can remove a data set.

You can use the **dmf** command to remove a data set:

```
dmf destroy dset [-r] [-f] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

-f Forces the action without confirmation.

-o *object*

Specifies the name of the object this command is addressed to.

-r Prints the **uuid** assigned to the request.

Perform the following steps to remove a data set using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Dataset management** → **Remove dataset**.

2. Specify the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell name** field and press Enter.
4. Enter the name of the data set in the **Dset name** field (or choose one from the list by pressing F4) and press Enter. A confirmation dialog displays.

Mounting data sets

You can mount a data set in the cell namespace to make it visible in this cell from NFS clients.

You can use the **dmf** command to mount a data set:

```
dmf mount dset mount_path [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

mount_path

Specifies the mount path in the namespace.

-o *object*

Specifies the name of the object this command is addressed to.

-r

Prints the **uuid** assigned to the request.

Perform the following steps to mount a data set using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Dataset management** → **Mount Dataset**.
2. Specify the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell name** field and press Enter.
4. Enter the name of the data set in the **Dset name** field and press Enter.
5. Specify the location where the data set will be mounted on this server in the **Mount path** field. The data set cannot be already mounted and the path cannot already exist.

Unmounting data sets

You can unmount a data set that was previously mounted. After a data set is unmounted, it is no longer visible in the cell namespace. For data set mounts that exist within replicated data sets, the unmount does not take effect until the associated replicas are updated.

You can use the **dmf** command to unmount a data set:

```
dmf unmount dset mount_path [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

mount_path

Specifies the mount path in the namespace.

- o object**
Specifies name of the object to which this command is addressed.
- r**
Prints the **uuid** assigned to the request.

Perform the following steps to unmount a data set using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Dataset management** → **Unmount Dataset**.
2. Specify the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell name** field and press Enter.
4. Enter the name of the data set in the **Dset name** field and press Enter.
5. Specify the location where the data set is currently mounted in the **Mount path** field and press Enter.

Creating and managing replicas

A *replica* is a read-only copy of a data set. You can distribute a replica across multiple data servers. You can create, remove, validate, update, list, mount, unmount, place, and unplace replicas and change their options.

Creating a replica of a data set

You can create a replica of a data set in a specified location on a server.

You can use the **dmf** command to create a replica:

```
dmf create replica name server [path] [-d | -w timeout] [-r] [-a admin_server] [-c container] [-o object]
```

where:

- a admin_server**
Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator
- c container**
Specifies the container (the cell name, for example).
- d**
Specifies that the command must be run asynchronously.
- name*
Specifies the name for the replica to be created.
- o object**
Specifies the name of the data set that will be the source of this replica.
- path*
Specifies the local path on the server. If the path parameter is omitted, the server puts the replica in its default pool for replicas.
- r**
Prints the **uuid** assigned to the request.
- server*
Specifies the name of the server where the replica will be created.
- w timeout**
Specifies how long the command can wait before completing.

You can use the **dmf** command to add a key/value item to a list-based attribute for a replica:

```
dmf add_to replica key=value [-r] [-a admin_server] [-c container] [-o object]
```

where:

- a admin_server**
Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c container
Specifies the cell name.

key=value
Specifies an attribute and the value to assign to it. Valid keys are **DmPrincipal**, **DmOwningRole**, and **DmTransferTable**.

-o object
Specifies the name of the object this command is addressed to.

-r Prints the **uuid** assigned to the request.

You can use the **dmf** command to remove a key/value item from a list-based attribute for a replica:

```
dmf remove_from replica key=value [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a admin_server
Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c container
Specifies the cell name.

key=value
Specifies an attribute and the value to assign to it. Valid keys are **DmPrincipal**, **DmOwningRole**, and **DmTransferTable**.

-o object
Specifies the name of the object this command is addressed to.

-r Prints the **uuid** assigned to the request.

Perform the following steps to create a replica using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Replica management** → **Create replica of a dataset**.
2. Enter the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter a cell name in the **Cell name** field (or choose one from the list by pressing F4).
4. Specify the source data set to be replicated in the **Dset name** field.
5. Enter a name for the replica in the **Replica name** field.
6. Specify the server on which the replica will be created in the **Server** field.
7. Specify the replica location in the **Root directory** field. If you do not specify a location, the replica will be located in the default replica path defined for the server. The default replica path is the path specified when the **dms** daemon is started by the **-ndaf_replica_default** parameter. If this parameter is not specified, the default path is **\$ndaf_dir/server/replicas**, where **\$ndaf_dir** is the path specified by the **-ndaf_dir** parameter. You can edit this path using the **dmf set DmDefaultRepPath** command in the NDAF CLI.

Showing and changing replica attributes

You can display the attributes of a replica. If you have the required authorization, you can modify the attributes of a replica.

You can use the **dmf** command to display the attributes for a replica:

```
dmf show replica [-r] [-a admin_server] [-c container] [-o object]
```

where:

- a** *admin_server*
Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.
- c** *container*
Specifies the cell name.
- o** *object*
Specifies the name of the object this command is addressed to.
- r**
Prints the **uuid** assigned to the request.

You can use the **dmf** command to change the attributes for a replica:

```
dmf set replica key=value [-r] [-a admin_server] [-c container] [-o object]
```

where:

- a** *admin_server*
Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.
- c** *container*
Specifies the cell name.
- key=value*
Specifies an attribute and the value to assign to it. Valid keys are **DmOwner**, **DmGroup**, **DmMode**, and **DmLocsMax**.
- o** *object*
Specifies the name of the object this command is addressed to.
- r**
Prints the **uuid** assigned to the request.

Perform the following steps to display and change the attributes for a replica using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Replica management** → **Change/show replica attributes**.
2. Enter the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field.
3. Enter the name of the cell in the **Cell name** field.
4. Enter the name of data set in the **Dset name** field. The following attributes display:

Admin server DNS name (or IP address)

Specifies the DNS name or IP address of the server.

Cell name

Specifies the name of the cell.

Dset name

Specifies the name of the data set.

Dset UUID

Specifies the universal unique identifier for the data set.

Version

Specifies the version number of the replica.

Owner

Specifies the owner of the data set root directory.

Group Specifies the group of the data set root directory.

Mode Specifies the mode that should be set for the data set root directory. The default mode is 755.

Maximum number of reported locations

Specifies the maximum number of NFS locations referrals that can be returned to an NFS client for an object.

NDAF principals

Specifies a list of users (separated by commas). These users own this data set and can manipulate the data set.

Owning roles

Specifies the roles that can manage the replica.

Transfer methods

Specifies the methods you want this data server to use for data transfer (or choose one from the list by pressing F4). You can specify multiple, comma-separated methods. Possible methods are **copy**, **rsync**, and **copy + rsync**. The default method is copy.

Placing a replica

You can create a copy of the master replica location at a specified location on the server and export the replica on this server under the cell.

You can use the **dmf** command to place a replica:

```
dmf place replica server_name [path] [-d | -w timeout] [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

-d

Specifies that the command must be run asynchronously.

-o *object*

Specifies the name of the object to which this command is addressed.

path

Specifies the path of the replica data on that server.

-r

Prints the **uuid** assigned to the request.

server_name

Specifies the server name where the replica data should be placed.

-w *timeout*

Specifies how long the command can wait before completing.

Perform the following steps to place a replica using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Replica management** → **Place replica**.
2. Enter the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell name** field (or choose one from the list by pressing F4) and press Enter.
4. Enter the name of the replica to place in the **Replica name** field (or choose one from the list by pressing F4).
5. Enter the name of the server where the replica will be placed in the **Server name** field.

- Specify the location where the replica will be copied in the **Local path on server** field. If you do not specify a location, the replica is copied in the default replica path defined for the server (defined in the **DmDefaultRepPath** attribute of the server).

Mounting a replica

You can mount a replica so that it is available at a specified location on a cell namespace.

You can use the **dmf** command to mount a replica:

```
dmf mount replica mount_path [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

mount_path

Specifies the mount path in the namespace.

-o *object*

Specifies the name of the object this command is addressed to.

-r

Prints the **uuid** assigned to the request.

Perform the following steps to mount a replica using SMIT:

- From the **NDAF** menu, select **NDAF Management** → **Data management** → **Replica management** → **Mount replica..**
- Enter the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
- Enter the name of the cell in the **Cell name** field and press Enter.
- Enter the name of the replica to be mounted in the **Replica name** field.
- Specify the location in the cell namespace where the replica will be made available in the **Mount path** field.

Updating a replica

A replica is a read-only copy of a data set, but you can update a replica so that the replica's contents are synchronized with the source data set.

You can use the **dmf** command to refresh a replica from its original source data set:

```
dmf update replica [-d | -w timeout] [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

-d

Specifies that the command must be run asynchronously.

-o *object*

Specifies the name of the object this command is addressed to.

-r

Prints the **uuid** assigned to the request.

-w *timeout*

Specifies how long the command can wait before completing.

Perform the following steps to refresh a replica from its original source data set using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Replica management** → **Update replica**.
2. Enter the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in which the replica is located in the **Cell name** field and press Enter.
4. Enter the name of the replica to update in the **Replica name** field and press Enter.

Validating a replica

Replica validation checks the consistency of the replica in the specified namespace.

You can use the **dmf** command to validate a replica:

```
dmf validate replica [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

-o *object*

Specifies the name of the object this command is addressed to.

-r

Prints the **uuid** assigned to the request.

Perform the following steps to validate a replica using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Replica management** → **Check replica**.
2. Enter the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell name** field and press Enter.
4. Enter the name of the replica to be checked in the **Replica name** field (or choose one from the list by pressing F4) and press Enter.

Unmounting a replica

You can unmount a previously mounted replica so that the replica is no longer available for use.

You can use the **dmf** command to unmount a replica:

```
dmf unmount replica mount_path [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

mount_path

Specifies the mount path in the namespace.

- o** *object*
Specifies the name of the object this command is addressed to.
- r** Prints the **uuid** assigned to the request.

Perform the following steps to unmount a replica using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Replica management** → **Unmount replica**.
2. Enter the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell name** field and press Enter.
4. Enter the name of the replica to unmount in the **Replica name** field.
5. Specify the location where the replica is currently mounted in the cell namespace in the **Mount path** field and press Enter.

Unplacing a replica

Unplacing a replica removes a replica placed on a data server at a specified location. After confirmation of removal of a replica, the data on the location specified by the path is destroyed and the path is unexported.

You can use the **dmf** command to unplace a replica:

```
dmf unplace replica server_name [path] [-r] [-f] [-a admin_server] [-c container] [-o object]
```

where:

- a** *admin_server*
Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.
- c** *container*
Specifies the cell name.
- f** Forces the action without confirmation.
- o** *object*
Specifies the name of the object this command is addressed to.
- path* Specifies the path of the replica data on that server.
- r** Prints the **uuid** assigned to the request.
- server_name*
Specifies the server name where the replica data should be unplaced.

Perform the following steps to unplace a replica using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Replica management** → **Unplace replica**.
2. Enter the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell name** field (or choose one from the list by pressing F4) and press Enter.
4. Enter the name of the replica to be unplaced in the **Replica name** field (or choose one from the list by pressing F4).
5. Enter the name of the server from which the replica will be removed in the **Server name** field.
6. Specify the location where the replica is currently copied on the server in the **Local path on server** field.

Removing a replica

Destroying a replica removes every location of the replica including its master location.

You can use the **dmf** command to remove a replica:

```
dmf destroy replica [-r] [-f] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

-f Forces the action without confirmation.

-o *object*

Specifies the name of the object this command is addressed to.

-r Prints the **uuid** assigned to the request.

Perform the following steps to remove a replica using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Replica management** → **Remove replica**.
2. Enter the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell name** field and press Enter.
4. Enter the name of the replica to be removed in the **Replica name** field and press Enter. A confirmation dialog displays.

Listing replicas

You can display a list of all replicas for a specified administration server and namespace.

You can use the **dmf** command to display a list of replicas:

```
dmf enumerate cell replica [pattern] [-r] [-a admin_server] [-c container]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

pattern

Optional matching text pattern. Valid values include ? and *.

-r Prints the **uuid** assigned to the request.

Perform the following steps to display a list of replicas using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Replica management** → **List replicas**.
2. Specify the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Select whether to list all replicas for a cell or for a server by choosing the appropriate option (by pressing F4) and press Enter.

4. Enter the cell name or server name in the **Cell name** or **Data server Name** field (you can press F4 to select a cell or a server from a list) and press Enter. If you do not specify a cell name or server name, all of the replicas for all cells or all data servers displays.

Changing the master replica

You can specify a replica location to become the master location.

You can use the **dmf** command to change the master replica:

```
dmf master replica server [path] [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

-o *object*

Specifies the name of the object this command is addressed to.

path Specifies the local path on the server.

-r Prints the **uuid** assigned to the request.

server Specifies the server name.

Perform the following steps to change the master replica using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Replica management** → **Change master replica**.
2. Enter the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell name** field (or choose one from the list by pressing F4) and press Enter.
4. Enter the name of the replica that will become the master replica in the **Replica name** field (or choose one from the list by pressing F4).
5. Enter the name of the server where the replica will be placed in the **Server name** field.
6. Specify the location where the replica will be copied in the **Local path on server** field. If you do not specify a location, the replica is copied in the default replica path defined for the server (the **DmDefaultRepPath** attribute of the server).

Changing the source of a replica

You can change the source data set for a replica.

You can use the **dmf** command to change the source data set of a replica:

```
dmf source replica new_source [-r] [-a admin_server] [-c container] [-o object]
```

where:

-a *admin_server*

Specifies the DNS name or IP address of the administration server. The port can be added using a colon separator.

-c *container*

Specifies the cell name.

-o *object*

Specifies the name of the object this command is addressed to.

new_source

Specifies the name of the new source data set.

-r Prints the **uuid** assigned to the request.

Perform the following steps to change the source data set of a replica using SMIT:

1. From the **NDAF** menu, select **NDAF Management** → **Data management** → **Replica management** → **Change the source of a replica**.
2. Enter the DNS name or IP address of the administration server that manages the NDAF domain in the **Admin name** field and press Enter.
3. Enter the name of the cell in the **Cell name** field (or choose one from the list by pressing F4) and press Enter.
4. Enter the name of the replica for which to change the source data set in the **Replica name** field (or choose one from the list by pressing F4).
5. Enter the name of the new source data set in the **New source dset name** (or choose one from the list by pressing F4) and press Enter.

Populating data sets

There are two basic approaches to populating newly created data sets with data: by local filesystem access on the server, or remotely by NFSv4. With the exception of replicas under NDAF control and the creation of data set references for data set mounts, the creation and manipulation of data inside filesystems with data sets uses normal filesystem access mechanism such as **libc** calls and NFS. The primary form of access to NDAF-managed filesystems is expected to be through NFS.

You can use local filesystem access to populate a new data set. If the path of the data set was specified when the data set was created, you can go to the specified directory on the server and create, restore, or copy the necessary data to the directory. When the data set is created in the default data set pool, the data set is created in the directory specified by the **-ndaf_dataset_default** parameter when the **dms** daemon is started on the server, or under **server/dsets** in the directory specified by the **-ndaf_dir** parameter if **-ndaf_dataset_default** is not specified. The directory name for the data set is generated by NDAF and is not obvious. You can locate the proper directory by running `dmf show dset` and inspecting the **DmPath** field. For example:

```
# dmf show dset -a admin_hostname -c my_cell -o my_dset | grep DmPath
DmPath: /ndafpool/dset/db2c3176-e5ed-11da-802d-0004ace4aa38
```


You can also use remote filesystem access to populate a new data set. After you have used the **dmf mount** command to place the data set in to the namespace, you can access the directory through an NFS client that mounts the root directory of any server on which the cell has been placed. You can go to the directory in the namespace where the data set was placed and create, restore, or remotely copy the data into the data set. You might need to run the **dmf set dset DmMode** to enable write access by the client. For example:

```
# dmf create dset my_dset1 my_server2 -a admin_hostname -c my_cell
# dmf place cell my_server2 -a admin_hostname -c my_cell
# dmf mount dset /mount_my_dset1 -a admin_hostname -c my_cell -o my_dset1
# dmf set dset DmMode=777 -a admin_hostname -c my_cell -o my_dset1
# mount -o vers=4 server_hostname:/mnt
# cd /mnt/my_cell/mount_my_dset1
```

Constructing a cell namespace from data sets

You can construct a cell namespace from data sets.

Creating a cell namespace from data sets (or replicas) involves creating the data sets (or replicas) with the **dmf create** command, and then using the **dmf mount** command to place them where needed in the namespace. For example, if you want to create data sets with the names **a**, **b**, **c**, and **d** and construct a namespace such as the following (where **x**, **y**, and **z** are arbitrary directory names):



You can enter the following set of commands:

```

# dmf create dset a my_admin -a admin_hostname -c my_cell
# dmf create dset b my_admin -a admin_hostname -c my_cell
# dmf create dset c my_admin -a admin_hostname -c my_cell
# dmf create dset d my_admin -a admin_hostname -c my_cell
# dmf mount dset /a -a admin_hostname -c my_cell -o a
# dmf mount dset /b -a admin_hostname -c my_cell -o b
# dmf mount dset /x/y/c -a admin_hostname -c my_cell -o c
# dmf mount dset /x/z/d -a admin_hostname -c my_cell -o d
  
```

If an NFSv4 client then mounts the root of an NDAF server on which the cell has been placed, the NFSv4 client will see the above directory structure.

Federating servers without NDAF into an NDAF environment

You can create an external non-NDAF managed server so that existing local filesystem data can be connected to an NDAF cell namespace. External servers are used to tie data from non-NDAF enabled servers or preexisting data on NDAF-enabled servers into the NDAF cell namespace.

Enter the following command to create a data set entry for **dset_ext1**, record the data set entry's accessible location (NFS-exported path) as **/export1/dset_extern** on **extern4**. This data is then NFS-exported on the **extern4** server at **/export1/dset_extern**. The external server path is the path from the root of that server's exported NFSv4 namespace to the exported directory.

```

dmf create server ndaf_extern4 extern4 -e -a soprane
dmf create dset dset_ext1 ndaf_extern4 /export1/dset_extern -a soprane -c ndaf_cell_1
  
```

This creates a data set entry for **dset_ext1** and records the data set entry's accessible location (NFS-exported path) on **extern4** as **/export1/dset_extern**. This data is NFS-exported on the **extern4** server at **/export1/dset_extern**. The external server path is the path from the root of the server's exported NFSv4 namespace to the exported directory.

For NFS servers, this exported directory must correspond to the root directory of the filesystem that is being NFS exported.

Enter the following command to create a data set reference for the external data set **dset_ext1** at **/ndaf_cell_1/extern** in the NFSv4 pseudo namespace of all of the servers that host **ndaf_cell_1**. When clients access **/extern** (assuming **/ndaf_cell_1** is mounted on the clients), the clients are redirected to **ndaf26:/export1/dset_extern**.

```

dmf mount dset /extern -a soprane -c ndaf_cell_1 -o dset_ext1
  
```

Troubleshooting NDAF

You can troubleshoot NDAF.

Table 1. Troubleshooting

Problem	Action
The dms or dmadm daemons won't start.	Must specify either <i>ndaf_dir</i> or both <i>ndaf_dataset_default</i> and <i>ndaf_replica default</i> when starting dms . Must specify <i>ndaf_dir</i> when starting dmadm . The specified directory for data sets and replicas must belong to a data-set enabled filesystem. Use dms_enable_fs to enable the filesystem. If using Kerberos, check the Kerberos keytab file.
Can read files, but can't create or modify data set files from NFS client.	The DmMode for the data set might not permit writes. To fix this, use <code>dmf set dset DmMode=<required mode></code>
Cannot navigate to the cell or data set directory or access data set data from NFS client.	All the following must be running on the NDAF data server: nfsd , nfsrgyd , and dms .
The dmf command fails with Cannot contact remote host message.	Make sure the hostname of the administration server is specified correctly in the dmf command and that the dmadm daemon is running on the administration server.
Cannot specify directory when creating a data set.	The specified directory must belong to a filesystem that has been enabled for data sets on the server with the dms_enable_fs command. The specified directory must not exist. Note: The directory will be created by the dmf command.
Source data set is down and a replica exists, but the client will not fail over to the replica.	This feature is not supported. Clients will fail over from one replica to another, but not from the source data set to a replica.
Failover from one replica to another takes too long or is too quick.	The timeout by default is approximately the <i>timeo</i> value multiplied by the <i>retrans</i> value (from the mount command or nfs4cl command). This can be overridden with the nfs_replica_failover_timeout option of the nfsd command.
Cell or data set is not NFS-exported.	Make sure nfsroot is set. The command to set it is: <code>chnfs -r <root_dir></code> To make the exports happen after setting the root, you must restart dms .
Cannot create a cell or data set.	Filesystem where the data set will be created must be enabled for data sets with the dms_enable_fs command.
Cannot see data in a the data set when mounted with NFSv4. Might be able to see the data when mounted from some servers, but not from others.	NFSv4 must be configured with replicas enabled on all NDAF servers. The command to enable NDAF servers is: <code>chnfs -R on</code>

NDAF checker

To help diagnose problems, NDAF provides commands to check the consistency of the databases used to manage the NDAF objects on administration and data servers.

You can use the following **dmf** command code to check the validity and consistency of the administration server database:

```
dmf check_adm admin [-r] [-a admin_server]
```

where:

-r Prints the **uuid** assigned to the request.

-a *admin_server*

Specifies the DNS name or IP address of the admin server. The port can be added using a colon separator.

You can use the following **dmf** command to check the validity and consistency of the data server database on the specified data server or on every managed data server if none is specified:

```
dmf check_serv server [-r] [-a admin_server] [-c container]
```

where:

-r Prints the **uuid** assigned to the request.

-a *admin_server*

Specifies the DNS name or IP address of the admin server. The port can be added using a colon separator.

-c *container*

Specifies the name of the server to check.

You can use the following **dmf** command to check the consistency of the database on the administration server with the database on the specified data server or with the databases on every managed data server if none is specified:

```
dmf check_adm_serv {admin|server} [-r] [-a admin_server] [-c container]
```

where:

-r Prints the **uuid** assigned to the request.

-a *admin_server*

Specifies the DNS name or IP address of the admin server. The port can be added using a colon separator.

-c *container*

Specifies the name of the server to check.

If the data from this command indicates inconsistencies between the databases, it might be necessary to recover from a backup to restore correct behavior. See “NDAF data backup” on page 40 and “NDAF data recovery” on page 40 for more information.

The following is sample output from running the following **dmf** command:

```
# dmf check_adm admin -a ndaf10

----- STARTING REPORT FROM SERVER my_admin -----
1      ERROR(S)
-----
----- DATABASE CHECK -----

ERROR: 1
DATABASE:      glodb:///admin/dmf.ldb
DESCRIPTION:
Error DmGroup root doesn't exist for DmUuid 8c9d4200-e973-11da-b214-de83e0005002 with path \
/var/dmf/server/dsets/8c9d416a-e973-11da-b214-de83e0005002

----- END OF REPORT FROM SERVER my_admin -----
```

The sample output shows that an NDAF object has a **DmGroup** parameter that is not valid. In this situation, use the **dmf show** command to find the corresponding data set, which is identified by the **DmUuid** parameter. In this case, the group specified for the data set is not valid because it does not exist in the **/etc/group** file. The solution might be to use the **dmf set dset** command to change this data set parameter.

NDAF data backup

An important consideration when backing up NDAF data is that the NDAF state data needs to be backed up along with the dataset data.

While normal means can be used to back up the dataset data (either locally on the server or remotely using NFS), it is recommended that the NDAF state data be backed up using a filesystem snapshot to get a consistent backup of the NDAF state data. This must be done locally on each data server and the administration server for that server's local state data. The directory to back up is the *ndaf_dir* specified when the **dms** or **dmadm** daemons were started. If this state data is lost, all data sets, replicas, and global namespace information will have to be recreated.

A data set replica could serve as a backup of dataset data in that the most recently updated replica could be copied back to the source data set location if necessary.

NDAF data recovery

Assuming the NDAF dataset data and state data is backed up as described above, recovery depends on what is lost.

If the filesystem itself is fine, missing or corrupted dataset data could be recovered by simply restoring from a backup. If more is required, such as if it is required to unexport the filesystem, then use the **dmf repair server** command with the **-unexport** option. After the unexport is done, you can destroy, recreate, and recover the filesystem from a backup. Finally, use the **dmf repair server** with the **-repair** option to recover the server and reexport the data sets within the filesystem.

If the NDAF state data must be recovered from a backup, use the **dmf repair server** with the **-repair** option after you recover the data from a snapshot.

The **dmf repair server** command can be run with no options or with the **-verify** option to produce a report of inconsistencies.

For more information about the **-repair** option, see the **dmf** command.

Additional NDAF command processes

There are additional commands.

NDAF uses three configuration commands to prepare systems for running its processes.

mkndaf

configures the system to run NDAF.

chndaf

changes various parameter settings used by the **dms** command and **dmadm** command.

rmndaf

configures the system to stop running NDAF daemons.

NDAF SMIT fastpaths

You can use SMIT fastpaths to go directly to your NDAF screen of choice, rather than navigate there screen by screen.

For more information about the underlying commands and syntax used by a particular screen to perform its task, see the `dmf` command and the `dms` command.

Table 2. NDAF SMIT fastpaths

Fastpath	Screen name	Function
ndaf	Network Data Administration Facility (NDAF)	Main NDAF menu. Enables centralized provisioning of data and its location and replication across a network of systems. When used with NFSv4 servers, enables construction of a single NFS namespace that covers multiple servers.
ndafconfig	NDAF Configuration	Starts and stops the administration daemons and enables and disables filesystems for data sets.
ndafmgmt	NDAF Management	Enables you to create, display, remove or change the attributes of NDAF entities such as administration and data servers, cell namespaces, data sets, replicas, and roles.
ndafadminconfig	Administration Server Configuration	Starts and stops dmadm and dms administration daemons.
ndafdataconfig	Data Server Configuration	Starts and stops dms administration daemon. Disables and enables filesystems for data sets.
ndafadmin	Administration Server Management	The administration server federates and manages the set of NFSv4 servers as a single system. You can create, remove, and change the attributes of the administration server.
ndafds	Data Server Management	NDAF uses data server systems to store data that it provisions. A data server process runs on each data server to carry out actions in underlying filesystems.
ndafcell	Namespace (Cell) Management	A cell is a collection of data sets organized into a single file namespace for use with NFSv4 servers. NFSv4 clients are expected to mount the root directory of the cell to access the cell's full namespace.
ndafdset	Dataset (dset) Management	Enables you to create, remove, validate, list, mount and unmount dsets, and change their attributes.
ndafrep	Replica Management	Enables you to create, remove, validate, update, list, mount, unmount, place and unplace replicas and change their attributes.
ndafrole	Delegation of Administration Rights	Enables you to create, list, remove, and change the attributes of roles, which are a set of privileges attached to a set of users that permit the users to manage the resources within a cell.
ndafadminstart	Start Administration Daemons	Starts the dms and dmadm daemons on the administration server.
ndafadminstop	Stop Administration Daemons	Stops the dms and dmadm daemons on the administration server.
ndafdatastart	Start Administration Daemon	Starts the dms administration daemon.
ndafdatastop	Stop Administration Daemon	Stops the dms administration daemon.

Table 2. NDAF SMIT fastpaths (continued)

Fastpath	Screen name	Function
ndafenablefs	Enable Filesystem for Datasets	Configures a filesystem so that it can be defined as a data set.
ndafdisablefs	Disable Filesystem for Datasets	Configures a filesystem so that it can no longer be used as a data set.
ndafadmincreate	Create Admin Server	Creates the master administration server of the NDAF domain that will be running the administration server daemon.
ndafadminremove	Remove Admin Server	Removes the administration server and cleans the server's databases of all the objects that have been defined within it.
ndafadminstatus	Show Admin Server Status	Displays the contents of the log of the administration server.
ndafadminclearstatus	Clear Admin Server Status	Clears the contents of the log of the administration server.
ndafdscreate	Create Data Server	Creates a data server within an administration server.
ndafcellcreate	Create Cell Namespace	Creates a cell namespace.

Appendix. Notices

This information was developed for products and services offered in the U.S.A.

IBM® may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
U.S.A.

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation
Dept. LRAS/Bldg. 003
11400 Burnet Road
Austin, TX 78758-3498
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106-0032, Japan

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

Trademarks

The following terms are trademarks of International Business Machines Corporation in the United States, other countries, or both:

AIX
AIX 5L
IBM
ibm.com

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product, or service names may be the trademarks or service marks of others.

Index

A

- ACE configuration 7
- adding servers for NDAF 13
- administration client 3
- administration server 3
 - adding 13
 - configuring 12
- attributes
 - showing and change role 18
 - showing and changing data set 23
 - showing and changing replica 28

B

- backing up data 40

C

- cell 2
 - adding a server 16
 - changing attributes 15
 - creating 14
 - listing 14
 - managing 14
 - removing 16
 - removing server from 17
 - showing attributes 15
- cell namespace
 - constructing from data sets 36
- changing
 - cell attributes 15
 - data set attributes 23
 - master replica 35
 - replica attributes 28
 - role attributes 18
 - source of a replica 35
- clients
 - administration 3
- clones 3
- commands 5
 - dmadm 5
 - dmf 5
 - dms 4, 6
 - dms_enable_fs 6
- configuring
 - an NDAF administration client 12
 - Kerberos 5 10
 - NDAF data servers 11
 - the NDAF administration server 12
- constructing cell namespace from data sets 36
- creating
 - a replica of a data set 27
 - cells 14
 - data sets 20, 21
 - external data set 37
 - replicas 27
 - roles 17

D

- data backup 40
- data centers 6
- data recovery 40
- data repair 40
- data server 4
 - adding 13
- data sets 1, 20
 - checking 22
 - constructing cell namespace from 36
 - creating 20, 21
 - creating a replica of 27
 - creating external 37
 - grouping 2
 - listing 21
 - managing 20
 - mounting 26
 - populating 36
 - removing 25
 - showing and changing attributes 23
 - showing locations 25
 - unmounting 26
- database validity and consistency
 - checking 38
- deployment 6
- destroying
 - replica 34
- dmadm command 5
- dmf check_adm 38
 - sample output 38
- dmf command 5
- dms command 4, 6
- dms_enable_fs command 6
- domain 1, 4
- dsets 1, 2

E

- exporting filesystems 7
 - Kerberos 7
- external data set
 - creating 37

F

- fastpaths 43

I

- installing 9
 - NDAF 9
 - NDAF when Kerberos 5 is required 9
 - ndaf.base fileset 9

K

- Kerberos
 - required services 5
 - security levels 11
- Kerberos 5
 - configuring 10

L

- listing
 - cell namespaces 14
 - replicas 34
 - roles 20
- location
 - master replica 2
- locations, showing data set 25

M

- managing
 - cells 14
 - data sets 20
 - NDAF 12
 - replicas 27
 - roles 17
- master replica
 - changing 35
 - removing/destroying 34
- master replica location 2
- mounting
 - data sets 26
 - replicas 31

N

- namespaces
 - listing cell 14
- NDAF administration client
 - configuring 12
- NDAF administration server
 - configuring 12
- NDAF data server
 - configuring 11
- NDAF overview 1
- NDAF servers
 - configuring for NFSv4 9
- ndaf.base fileset 9
- NFS security 7
- NFSv4
 - configuring 9

P

- PFS 1
- physical filesystem (PFS) 1
- placing 2
 - replicas 30
- populating data sets 36
- port requirements 11
- principals 4, 8

- principals (*continued*)
 - service 10

R

- recovery, data 40
- removing
 - cell namespace 16
 - data set 25
 - replica 34
 - role 19
 - server from a cell namespace 17
- repair, data 40
- replica 2
 - changing the source of 35
 - creating 27
 - listing 34
 - managing 27
 - master 2
 - mounting 31
 - placing 3, 30
 - removing/destroying 34
 - showing and changing attributes 28
 - unmounting 32
 - unplacing 33
 - updates 3
 - updating 3, 31
 - validating 32
- role 8, 17
 - creating 17
 - listing 20
 - managing 17
 - removing 19
 - showing and changing attributes 18
- RPC port requirements 11

S

- server
 - adding for NDAF 13
 - adding to a cell 16
 - administration 3
 - data 4
 - removing from cell 17
- service principals 10
- setting up
 - NDAF administration clients 12
 - NDAF data servers 11
 - the NDAF administration server 12
- showing
 - cell attributes 15
 - data set attributes 23
 - data set locations 25
 - replica attributes 28
 - role attributes 18
- SMIT fastpaths 43
- source
 - changing a replica's 35

T

troubleshooting 38

U

unmounting
 a replica 32
 data sets 26
unplacing a replica 33
updating
 replicas 3, 31

V

validating a replica 32

W

WANs 6
wide-area networks 6

Readers' Comments — We'd Like to Hear from You

AIX 5L Version 5.3
AIX Network Data Administration Facility

Publication No. SA23-2222-00

We appreciate your comments about this publication. Please comment on specific errors or omissions, accuracy, organization, subject matter, or completeness of this book. The comments you send should pertain to only the information in this manual or product and the way in which the information is presented.

For technical questions and information about products and prices, please contact your IBM branch office, your IBM business partner, or your authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you. IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you state on this form.

Comments:

Thank you for your support.

Submit your comments using one of these channels:

- Send your comments to the address on the reverse side of this form.
- Send your comments via e-mail to: aix6koub@austin.ibm.com

If you would like a response from IBM, please fill in the following information:

Name

Address

Company or Organization

Phone No.

E-mail address



Fold and Tape

Please do not staple

Fold and Tape



NO POSTAGE
NECESSARY
IF MAILED IN THE
UNITED STATES

BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

IBM Corporation
Information Development
Department 04XA-905-6C006
11501 Burnet Road
Austin, TX 78758-3493



Fold and Tape

Please do not staple

Fold and Tape



Printed in U.S.A.

SA23-2222-00

