

XtAppSetFallbackResources – set fallback resources

```
void XtAppSetFallbackResources(app_context, specification_list)  
    XtAppContext app_context;  
    String* specification_list;
```

app_context Specifies the application context.

specification_list Specifies a NULL-terminated list of resource specifications to pre-load the database, or NULL.

Each entry in *specification_list* points to a string in the format XrmPutLineResource. following a call to **XtAppSetFallbackResources**, when a resource database is being created for a particular screen and the Intrinsics are not able to find or read an application-specific class resource file and if *specification_list* is not NULL the resource specification in *specification_list* will be merged into the screen resource database in place of the application-specific class resource file. **XtAppSetFallbackResources** is not required to copy *specification_list*; the caller must ensure that the contents of the list and the strings addressed by the list remain valid until all displays are initialized or until **XtAppSetFallbackResources** is called again. The value NULL for *specification_list* removes any previous fallback resource specification for the application context. The intended use for fallback resources is to provide a minimal number of resources that will make the application usable (or at least terminate with helpful diagnostic messages) when some problem exists in finding and loading the application defaults file.

X Toolkit Intrinsics – C Language Interface

Xlib – C Language X Interface